


Xseries Firmware Programming

Download the Xseries Firmware Programmer from the website

www.docupen.it/install

Extract the download and run the Xseries Firmware Programmer executable file (InstallWinPenProgSolo.EXE). Follow instructions by the installation wizard to complete installation.


After the installation is complete, go to your PC Start→Planon→WinPenProgSolo to open the Xseries Firmware Programmer.




Connect DocuPen Xseries scanner to PC with USB cable

On your DocuPen Xseries scanner Press and hold the Power button and the Bluetooth button together, until the LCD screen displays the word "BOOTLOADER"


Then click "Program"



Enter authorization code: solo



Please do not disconnect pen while in programming mode



After the programming has successfully completed disconnect the DocuPen Xseries scanner from your PC and close the Xseries Firmware Programmer.

